# 一,Python环境安装

- Anaconda集成环境
- Python3.7

如果是linux环境包括MacOs,系统环境中会默认安装python2.7.

尽量不要卸载linux环境中的默认python环境,直接安装Python3.7即可,不过以后使用时需要指明python3

### 我使用的环境

系统: macOs

版本: Python3.7

IDE: Pycharm, Sublime

笔记: Typora (markdown)

## 1.windows系统安装Python3.7

- 1. 到官网下载对应的Python版本(64位,32位),官网: <a href="https://www.python.org/downloads/windows/">https://www.python.org/downloads/windows/</a>
- 2. 下载后选择安装,和普通软件安装一样
- 3. 注意安装过程中要 勾选 Add python to PATH 添加路路径
- 4. 安装后启动 cmd 命令行输入 python -V 检查版本是否安装成功

#### 图文安装步骤说明

1. 在python的官网下载python对应版本:

Python官网下载地址: <a href="https://www.python.org/downloads/windows/">https://www.python.org/downloads/windows/</a>

64位下载Windows x86-64 executable installer 版本

32位下载Windows x86 executable installer 版本

打开链接如下图,版本会一直更新,选择任意一个适合自己电脑的版本就好

# **Python Releases for Windows**

- · Latest Python 3 Release Python 3.7.0
- Latest Python 2 Release Python 2.7.15
- Python 3.7.0 2018-06-27
  - Download Windows x86 web-based installer
  - Download Windows x86 executable installer
  - Download Windows x86 embeddable zip file
  - Download Windows x86-64 web-based installer
  - Download Windows x86-64 executable installer
  - Download Windows x86-64 embeddable zip file
  - Download Windows help file
- Python 3.6.6 2018-06-27


https://blog.csdn.net/weixin 40844416

2. 勾选 Add python to PATH 添加路径

安装界面点击Customize installation 自定义安装




3. 不改变默认进行Next下一步




4. 选择一个自己喜欢的安装位置

#### 点击Install开始安装




5. 等待进度条加载完毕



6. 安装完毕,点击Close关闭

若方框位置出现管理员字样则点击授权再关闭



7. 验证: 运行cmd

进入到自己的安装目录下,运行语句:python-V

若显示出Python对应版本则表示安装成功

```
Microsoft Windows [版本 10.0.16299.15]
(c) 2017 Microsoft Corporation。保留所有权利。

C:\Users\Administrator>d:

D:\>python -V
ython 3.7.0b3

D:\> https://blog.csdn.net/weixin_40844416
```

## 2.ubuntu 系统安装Python3.7

1. 执行以下命令 更新源

```
sudo apt-get update
sudo apt-get upgrade
```

2. 安装python3.7

```
sudo apt-get install python3.7
```

3. 检测当前环境

```
python -V
# Python 2.7.10 # linux环境下的默认环境

python3 -V # 新安装的python3环境
# Python 3.7.4
```

## 3.macOs系统安装Python3.7

Mac电脑OSX系统自带Python, 但版本是2.7

打开终端输入 python -V

我们看到系统默认的Python版本是2.7.10,使用Homebrew安装

1. 打开命令行输入

```
brew install python3
```

2. 输入以下命令检查环境

```
python -V
# Python 2.7.10 # macOs环境下的默认环境

python3 -V # 新安装的python3环境
# Python 3.7.4
```

#### tip:如果mac系统没有安装Homebrew,打开命令行输入以下内容安装

```
# 安装 Homebrew
/usr/bin/ruby -e "$(curl -fsSL
https://raw.githubusercontent.com/Homebrew/install/master/install)"

# 卸载 Homebrew
/usr/bin/ruby -e "$(curl -fsSL
https://raw.githubusercontent.com/Homebrew/install/master/uninstall)"
```

### 二,IDE环境安装

- 1. pycharm安装
  - o pycharm官网 <a href="https://www.jetbrains.com/pycharm/">https://www.jetbrains.com/pycharm/</a>
- 2. sublime安装
  - sublime官网 <a href="http://www.sublimetext.com/3">http://www.sublimetext.com/3</a>
- 3. markdown工具Typora安装
  - Typora官网 <a href="https://www.typora.io/">https://www.typora.io/</a>